



Service Information

Offboard Diagnostic Information System Service (ODIS Service)

Number: VOS-25-04

Subject: DA 0015 AU Golf & A3 Passat DTC B10001B Hotfix
Instructions

Date: Jan 8. 2025

Supersedes VOS-24-129 due to updated information.

Important:

We recommend installation of this hotfix on one diagnostic device ONLY. Hotfix must be removed immediately after performing the procedure.

1.0 – Introduction

The hotfix is for the DA 0015 AU Golf 2015-2021 and A3 Passat 2012-2022. DTC B10001B. Driver airbag igniter resistance too high -N95

If the Basic Settings fail, you should let the car set for 30 minutes with the key on in order to “unlock” the ECU.

!! The Hotfix must be removed after performing the diagnostic procedure. !!

2.0 – Prerequisite

ODIS Service **latest Diagnostic Content version** must be installed.

To confirm the installed diagnostic content version in ODIS Service, go to:


Info >  Versions>Diagnostic data; didb_GFS-v.en_US: xxxxxxxx **X.XX.XX**




Service Information

3.0 – Download Hotfix

1. Open a **Web Browser** on the diagnostic device and logon to **vwhub.com**
2. Navigate to **Elsa2Go>Service References>Software/Hardware Updates**
3. Search for **DA 0015 AU Golf A3 Passat Hotfix Zip File**
4. Click the **DA 0015 AU Golf A3 Passat Hotfix Zip File** and **save** it to your Windows desktop.
5. Close your browser.
6. Browse to the desktop and double-click the **DA 0015 AU Golf A3 Passat Hotfix Zip File** to open it.
7. Right click the file (example only) name and select **Copy**:



8. Right click anywhere on the Windows desktop and select **Paste**. This file icon (example) must appear on the desktop:




(continued)




Service Information

4.0 – Install Hotfix into ODIS Service

1. Open ODIS Service (“Run as Administrator”)
2. Expand the **Data** submenu and click **Download** (under **Hotfix**):



3. Click **Continue**:




(continued)




Service Information

4. The Directory selection window will appear. Browse to and **highlight the Hotfix file** (*example only*), then click **Select Folder**:



5. Click **OK**:



6. Perform the diagnostic procedure.

Important:

The Hotfix must be removed after performing the procedure. Failure to do so will cause other vehicle diagnostics sessions to malfunction.


(continued)




Service Information

5.0 – Uninstall the Hotfix from ODIS Service

1. Select **Erase** (under Hotfix), then **Continue**:



2. Click **OK** and close ODIS Service:



Please contact Diagnostic Tester Software Support by phone at 888-896-1298 or email softwaresupport@vw.com with any questions or concerns.