



Service Information

Offboard Diagnostic Information System Service (ODIS Service) Number: AOS-26-09

Subject: **P275300 Transmission Fluid Cooler Circuit/Open Test Plan Hotfix Instructions** Date: Feb. 23, 2026

Hotfix Alert!

Issue seen: P275300 Transmission Fluid Cooler Circuit/Open fault stored with no relevant Test Plan populated.

- Vehicle effected: 2023 Q7_SQ7 vehicles
- Hotfix number: A_2.40.3_N488_20260220-072237
- ODIS software version needed for this hotfix: Audi brand version 2.40.3

Important:

We recommend installation of this hotfix on one diagnostic device ONLY. Hotfix must be removed immediately after performing the procedure.

1.0 Download Hotfix



1. Open a **Web Browser** on the diagnostic device and log on to **AccessAudi.com**
2. Navigate to **Elsa2Go>Service References>Software/Hardware Updates**
3. Search for **AOS-26-09 P275300 Transmission Fluid Cooler Circuit/Open Test Plan Hotfix Zip File**
4. Click the **AOS-26-09 P275300 Transmission Fluid Cooler Circuit/Open Test Plan Hotfix Zip** File icon  and **save** it to your downloads folder.
5. Close your browser.

(continued)




Service Information


6. Browse to your downloads folder and unzip the file the **AOS-26-09 P275300 Transmission Fluid Cooler Circuit/Open Test Plan Hotfix Zip**.



7. After unzipping the file, double-click on the file to open it.



8. Right click the file (example only) name and select **Copy**:






Service Information

9. Navigate to your computer desktop, right click anywhere on the Windows desktop and select **Paste**. This file icon (example) must appear on the desktop:




2.0 – Install Hotfix into ODIS Service

1. Open ODIS Service (“Run as Administrator”)
2. Expand the **Data** submenu and click **Download** (under **Hotfix**):



3. Click **Continue**:




(continued)




Service Information

4. The Directory selection window will appear. Browse to your Desktop and **highlight the Hotfix file (example only)**, then click **Select Folder**:



5. Click **OK**:



6. **Perform the diagnostic procedure.**

Important:


The Hotfix must be removed after performing the procedure. Failure to do so will cause other vehicle diagnostics sessions to malfunction.




Service Information

3.0 – Uninstall the Hotfix from ODIS Service

1. Select **Erase** (under Hotfix), then **Continue**:



2. Click **OK** and close ODIS Service:



For questions or concerns, please reach out to David Provonche, 248-754-6091.

extern.dave.provonche@audi.com

Audi GFF / ODIS Validation / Service42 Research

VWGoA, Inc.

Product Quality & Technical Service